

PowerOLAP® Version 22



Version 22 Upgrade (from V18)

Server and Client



This page has been left blank intentionally.



PowerOLAP Version 22

UPGRADE GUIDE

Topics

- PowerOLAP Server V22 Upgrade (from V18)
- PowerOLAP Client V22 Upgrade (from V18)



Information in this document and in documents associated with other PARIS Technologies technical materials is subject to change without notice and does not represent a commitment on the part of PARIS Technologies. No part of this document may be reproduced or transmitted in any form, or by any means whatsoever, without the written permission of PARIS Technologies International, Inc.

© Copyright 2022 PARIS Technologies International, Inc.

Windows is a trademark of the Microsoft Corporation.

Microsoft Excel is a trademark of the Microsoft Development Corporation.




© 2022 PARIS Technologies International, Inc.




1. PowerOLAP® Server Version 22 Upgrade (from Version 18)

NOTE: PARIS Technologies will provide you with a download of the setup files for PowerOLAP® Version 22

- 1. RECOMMENDED: Close and back up all PowerOLAP Server files.
- 2. Go to **Task Manager** and select the **Services tab**.
- 3. Locate PowerOLAP Server; right-click on it and select Stop.



Once stopped, the service will look as follows:



- 4. Locate the **setup file** for the PowerOLAP Server; if required, unzip.

 [Note: the PowerOLAP Server program may be 32 or 64bit; the following images show 32bit, but the same procedure applies for 64bit].
- 5. Right-click on the setup.exe; select Run as Administrator (see following image).







- You will be asked if you want to allow this app to make changes to your device; click Yes.
- 7. The PowerOLAP Server InstallShield Wizard screen will appear (as below). Click **Next** to proceed.



8. The License Agreement and Maintenance Agreement screens (next two images) will appear. To proceed, Accept the agreements by clicking Next.








9. You will be notified that the installation/update to PowerOLAP Version 22 is completed (see next image).





- 10. Click Finish.
- 11. Return to **Task Manager** and click on the **Services** tab. Find PowerOLAP Server: rightclick and select **Start**.



Ensure that the Server is Running, as shown circled below:




12. Go to the Windows Start button and start typing **PowerOLAP Service Control Program**. <u>IMPORTANT:</u> **Right-click** and **Run as Administrator** (as shown in the next image).





13. You will be asked if you want to allow this app to make changes to your device; click **Yes**.

The **PowerOLAP Server Version 22** screen will appear—<u>your Server upgrade is completed!</u> At this point you may wish to open PowerOLAP files on the Server.





2. PowerOLAP® Client Version 22 Upgrade (from Version 18)

- Save your work in PowerOLAP and Excel and close both programs.
 Stop the PowerOLAP Service Control Program (see Steps 2 and 3 in previous section)
- 2. Locate the **setup file** for the PowerOLAP Client; if required, unzip.
- 3. Right-click on the setup.exe; select Run as Administrator, as in the following image.




- 4. You will be asked if you want to allow this app to make changes to your device; click Yes.
- The PowerOLAP Client Components InstallShield Wizard screen will appear (as below). Click Next to proceed.





The License Agreement and Maintenance Agreement screens (next two images) will appear. To proceed, Accept the agreements by clicking Next.






7. You will be notified that the installation/update to PowerOLAP Version 22 is completed (see next image).



Page



8. Go to the Windows Start button and start typing **PowerOLAP**. IMPORTANT: **Right-click** and **Run as Administrator**, as shown below.



The PowerOLAP Version 22 splash screen will appear (see image next page) and the program will launch: <u>your PowerOLAP Client upgrade is completed</u>.





PowerOLAP Version 22 splash screen